

FIGURE 1
PRIOR ART




FIGURE 2




FIGURE 4

wfIpMrtmInjectRtTable OBJECT-TYPE
 SYNTAX SEQUENCE OF WfIpMrtmInjectRtEntry
 ACCESS not-accessible
 STATUS mandatory
 DESCRIPTION
 "The Table of MRTM Inject Unicast routes Policy Rules"
 ::= { wfIpPolicyGroup 21 }

wfIpMrtmInjectRtEntry OBJECT-TYPE
 SYNTAX WfIpMrtmInjectRtEntry
 ACCESS not-accessible
 STATUS mandatory
 DESCRIPTION
 "An entry in the Mrtm Inject Route Rule Table"
 INDEX { wfIpMrtmInjectRtIndex }
 ::= { wfIpMrtmInjectRtTable 1 }

WfIpMrtmInjectRtEntry ::= SEQUENCE {
 wfIpMrtmInjectRtDelete
 INTEGER,
 wfIpMrtmInjectRtDisable
 INTEGER,
 wfIpMrtmInjectRtIndex
 INTEGER,
 wfIpMrtmInjectRtName
 DisplayString,
 wfIpMrtmInjectRtNetworks
 OCTET STRING,
 wfIpMrtmInjectRtAction
 INTEGER,
 wfIpMrtmInjectRtPreference
 INTEGER,
 wfIpMrtmInjectRtPrecedence
 INTEGER,
 wfIpMrtmInjectRtInject
 OCTET STRING,
 wfIpMrtmInjectRtInInterface
 OCTET STRING,
 wfIpMrtmInjectRtType
 INTEGER,
 wfIpMrtmInjectRtMetric
 INTEGER

wfIpMrtmInjectRtDelete OBJECT-TYPE
 SYNTAX INTEGER {
 create(1),
 delete(2)
 }
 ACCESS read-write
 STATUS mandatory
 DESCRIPTION
 "Create/Delete parameter."
 DEFVAL { create }
 ::= { wfIpMrtmInjectRtEntry 1 }

FIGURE 5A

```

wfiPmrtmInjectRtEnable OBJECT-TYPE
    SYNTAX  INTEGER {
        enabled(1),

        disabled(2)
    }
    ACCESS  read-write
    STATUS  mandatory
    DESCRIPTION
        "Enable/Disable parameter."
    DEFVAL  { enabled }
    ::= { wfiPmrtmInjectRtEntry 2 }

```

```

wfiPmrtmInjectRtIndex OBJECT-TYPE
    SYNTAX  INTEGER
    ACCESS  read-only
    STATUS  mandatory
    DESCRIPTION
        "Rule index number"
    ::= { wfiPmrtmInjectRtEntry 3 }

```

```

wfiPmrtmInjectRtName OBJECT-TYPE
    SYNTAX  DisplayString
    ACCESS  read-write
    STATUS  mandatory
    DESCRIPTION
        "Rule name - user specified name for this rule"
    ::= { wfiPmrtmInjectRtEntry 4 }

```

```

wfiPmrtmInjectRtNetworks OBJECT-TYPE
    SYNTAX  OCTET STRING
    ACCESS  read-write
    STATUS  mandatory
    DESCRIPTION
        "Network identification list. This identifies which
        networks will match this rule. If non-null, The octet
        string contains one or more 3-tuples of this form:

        first octet:  exact (1) or range (2)
        next 4 octets: network number
        next 4 octets: network mask

```

An entry with an 'exact' tag means to only match the specific network advertisement (number & mask). An entry with a 'range' tag means to match any network number that falls in the range indicated by the number and mask.

A null string also means 'match any route'."

```

::= { wfiPmrtmInjectRtEntry 5 }

```

FIGURE 5B

wfIpMrtmInjectAction OBJECT-TYPE

SYNTAX INTEGER {
 accept(1),
 ignore(3)
}

ACCESS read-write

STATUS mandatory

DESCRIPTION

"action. 'accept' means that the route should be

imported from RTM to the Mrtm routing table. 'ignore'
means don't consider the route"

DEFVAL { accept }

::= { wfIpMrtmInjectRtEntry 6 }

wfIpMrtmInjectRtPreference OBJECT-TYPE

SYNTAX INTEGER(0..16)

ACCESS read-write

STATUS mandatory

DESCRIPTION

"preference. This is a metric to be used to compare
the preference path between inject route or the existing
route in Mrtm routing table. If the injecting unicast
route is preferred, then the value need to be set higher than
the preference of the existing route.
If the injecting unicast route path is preferred,
then the value need to be set greater than 0.

This parameter only has meaning if the action is 'accept'."

DEFVAL { 1 }

::= { wfIpMrtmInjectRtEntry 7 }

wfIpMrtmInjectRtPrecedence OBJECT-TYPE

SYNTAX INTEGER

ACCESS read-write

STATUS mandatory

DESCRIPTION

"precedence. This is a metric to be used to compare
this policy rule to other rules that a given route may
match. A rule with a higher precedence value will be
chosen over one with a smaller value. In the case of
a tie, the rule index is used (larger wins).

Note that the policy match is not most specific
so the precedence has to be used to select from
multiple matches."

::= { wfIpMrtmInjectRtEntry 8 }

FIGURE 5C

2023

DESCRIPTION

```
::= { wfIpMrtmInjectRtEntry 9 }
```

DESCRIPTION

```
::= { wfIpMrtmInjectRtEntry 10 }
```

FIGURE 5D

wfIpMrtmInjectRtType OBJECT-TYPE

```
SYNTAX INTEGER {
    static-route(1),
    rip(15),
    egp(16),
    ospf(17),
    bgp(18),
    direct-route(40),
    best-route(41),
    all-route(42)
}
ACCESS read-write
STATUS mandatory
DESCRIPTION
    "Select the injected route type from RTM. The value of each
    route type will be the same as unicast route type. See
    define in ip_rt_types.h"
DEFVAL { best-route }
 ::= { wfIpMrtmInjectRtEntry 11 }
```

wfIpMrtmInjectRtMetric OBJECT-TYPE

```
SYNTAX INTEGER (1..31)
ACCESS read-write
STATUS mandatory
DESCRIPTION
    "Route Metric. This value represents the cost of the external
    routes which are OSPF or unicast best route to be injected
    into Mrtm routing table. The default value is set to 1."
DEFVAL { 1 }
 ::= { wfIpMrtmInjectRtEntry 12 }
```

wfMrtm OBJECT IDENTIFIER ::= { wfMrtmGroup 1 }

wfMrtmCreate OBJECT-TYPE

```
SYNTAX INTEGER {
    created(1),
    deleted(2)
}
ACCESS read-write
STATUS mandatory
DESCRIPTION
    "Create/Delete parameter. Default is created.
    Users perform a set operation on this
    object in order to create/delete MRTM table."
DEFVAL { created }
 ::= { wfMrtm 1 }
```

FIGURE 5E

wfMrtmEnable OBJECT-TYPE

SYNTAX INTEGER (
 enabled(1),
 disabled(2)
)

ACCESS read-write

STATUS mandatory

DESCRIPTION

"Enable/Disable Parameter indicates whether
this MRTM record is enabled or disabled."

DEFVAL { enabled }

::= { wfMrtm 2 }

wfMrtmState OBJECT-TYPE

SYNTAX INTEGER (
 up(1),
 down(2),
 init(3),
 notpres(4)
)

ACCESS read-only

STATUS mandatory

DESCRIPTION

"The current state of the entire MRTM."

DEFVAL { notpres }

::= { wfMrtm 3 }

wfMrtmDebug OBJECT-TYPE

SYNTAX INTEGER

ACCESS read-write

STATUS mandatory

DESCRIPTION

"This is a debug field for PGM. Setting bits
cause PGM to generate certain log messages.

This field will NOT restart PGM.

The follow bits maybe set in any combination
(LS stands for least significant):

0x00000001 for no display

0x00000002 for interface to RTM

0x00000004 for interface to policy

0x00000008 for interface to multicast protocols

0x00000010 for route change or add or delete.

::= { wfMrtm 4 }

FIGURE 5F

wfMrtmHoldDownTime OBJECT-TYPE
 SYNTAX INTEGER(10..60)
 ACCESS read-write
 STATUS mandatory
 DESCRIPTION

"This value specifies, in seconds, how long a route
 will be held in MRTM table after it becomes unreachable."

DEFVAL { 10 }
 ::= { wfMrtm 5 }

wfMrtmFifoSize OBJECT-TYPE
 SYNTAX INTEGER(1..100)
 ACCESS read-write
 STATUS mandatory
 DESCRIPTION

"This value represents the depth of the FIFO
 between RTM and MRTM used for the outstanding route changes.
 The memory will be pre-allocated as the size of
 x times 1000 of FIFO route entry."

DEFVAL { 5 }
 ::= { wfMrtm 6 }

wfMrtmEstimatedNetworks OBJECT-TYPE
 SYNTAX INTEGER(10..200000)
 ACCESS read-write
 STATUS mandatory
 DESCRIPTION

"This parameter indicates the estimated number of routes
 per slot that the router will need to keep in its routing
 table. This value is used for pre-allocating routing tables."

::= { wfMrtm 7 }

wfMrtmMaxRoutes OBJECT-TYPE
 SYNTAX INTEGER
 ACCESS read-write
 STATUS mandatory
 DESCRIPTION

"Max number of routes, per slot. This is used to limit
 the size of routing tables. Note that routes are kept on a
 per-source network basis, independent of multicast group."

::= { wfMrtm 8 }

wfMrtmActualRoutes OBJECT-TYPE
 SYNTAX INTEGER
 ACCESS read-only
 STATUS mandatory
 DESCRIPTION

"Total actual entries currently in the routing table"

::= { wfMrtm 9 }

FIGURE 56